


Logging in


When do you need to log into the Xen host?

Logging into the Xen host is different to logging into your VPS, a guest machine. One of the first things you need to do when you've become a member is get your VPS up and running!

```
ssh username@console.soleus.nu
```



```
donna@polder: ~  
File Edit View Search Terminal Help  
perl: warning: Setting locale failed. 10/07/18  
perl: warning: Please check that your locale settings: 10/07/18  
LANG = "en_GB:en", LC_CTYPE = "en_GB.UTF-8", 10/07/18  
LC_ALL = (unset),  
LC_MONETARY = "nl_NL.UTF-8",  
LC_ADDRESS = "nl_NL.UTF-8",  
LC_TELEPHONE = "nl_NL.UTF-8",  
LC_NAME = "nl_NL.UTF-8",  
LC_MEASUREMENT = "nl_NL.UTF-8",  
LC_IDENTIFICATION = "nl_NL.UTF-8",  
LC_NUMERIC = "nl_NL.UTF-8",  
LC_PAPER = "nl_NL.UTF-8",  
LANG = "en_GB.UTF-8"  
Netzare supported and installed on your system.  
perl: warning: Falling back to a fallback locale ("en_GB.UTF-8").  
Xen-Shell v1.9 - Modified for Soleus  
xen-shell>  
xen-shell>  
xen-shell>_console  
Running console for branon - exit with Ctrl+]  
(You might need to press return a couple of times to see activity.)  
  
0 Xen Console 16:37  
0$* Xen Console
```



```
donna@polder: ~  
File Edit View Search Terminal Help  
xen-shell>_help  
Xen-Shell v1.9 - Modified for Soleus  
The following commands are available within this shell:  
  
bandwidth - Show your bandwidth usage.  
boot - Boot the Xen guest.  
console - Gain access to a Xen guest via the serial console.  
exit - Exit the shell.  
help - Show general, or command-specific, help information.  
pause - This will pause the Xen guest.  
quit - Exit this shell.  
reboot - Reboot the Xen guest.  
serial - Gain access to the Xen guest via the serial console.  
shutdown - Shutdown the Xen guest.  
status - Show the status of the Xen guest.  
sysreq - Send a 'sysreq' keystroke to the guest.  
top - Show system resource usage.  
unpause - This will unpause the Xen guest.  
uptime - Show the uptime information of your guest system and this host.  
version - Show the version of this shell, and of Xen.  
whoami - Show the user you're connected to the host system as.  
  
For command-specific help run "help command".  
  
xen-shell>  
0 Xen Console 16:31  
0$* Xen Console
```

Exit the login prompt with the following key combination: **Ctrl +]**